

Description

This support's manual contains some information about the delete and send file messages.

1. Delete file messages.


You have to enter in application NEOc.

USER: default


Password: 1234




First you must Search Devices.




Select device where you want work and press the button import system.



In the window principal you must press first the button Voice Alarm System. In the left will appear several options. You must press the option Messages.




Press the message that you will delete and Remove selected. For Example in the image select “REC_AL” and press Remove selected.




2. Send File Messages.

You must press “Sending audio files...” It will appear the windows for load audio. You press Add and search file that you want load.



Once loaded the file you can change the message type. Select the file and press the button set EVAC or Set ALERT.



Please contact with LDA Support Department for any information

support@lda-audiotech.com